


Introduction to Mobile Robotics with MATLAB and Simulink Unit 5: Using a Distance Sensor

By MathWorks Student Competition team



Distance Sensor

Ultrasonic distance sensors are commonly used in robotics and can give you information regarding the proximity of a nearby object

Robotics Playground - Distance Sensor



Description


This block returns the distance in meters to a nearby object such as walls and obstacles. Several sensor properties can be adjusted from the block mask, but default values can also be used.


Distance



Visualizing the Sensor Output


- Open the "AvoidWall_start"
- 2. Run the model
- Observe the Simulink Display connected to the distance (The value in meters to the closest object in real-time)
- 4. Stop the model








Using a Switch block




- Modify the model to prevent the robot from colliding into the wall.
- The switch block is the equivalent to an IF statement for different signals in Simulink
- Place a switch block in the model.
- 2. Connect the sensor distance to the switch block
- 3. Connect two constants to the switch block





Picking a Distance Threshold


- Open the switch block settings and change the switching threshold to 1 meter
- Run the model
- Adjust parameters if necessary to avoid colliding with the wall





Tracking the Wall


- Use the information from one distance sensor to track the walls within the field
- 1. Open the "TrackWall_start" model
- 2. Add a second switch that makes the robot turn when it is too close to a wall






Using Another Switch Block

- Connect the signal from the distance sensor to the second switch input
- Connect appropriate constants to the remaining switch block inputs
- Run the model
- Adjust constants and thresholds to have the robot track the walls





End of Unit 5: Using a Distance Sensor

- Congrats!
- Here are some learning outcomes from this unit
 - How to use a distance sensor
 - How to implement switching logic
 - How to track a wall with one sensor